


ManGo Upgrade Manual


Install USB-to-Serial Driver

- 1 Install “**PL2303_Prolific_DriverInstaller_v130.exe**” from the provided CD on your computer.



- 2 Connect the USB cable to your computer. (Don't connect USB cable to ManGo at this moment)
- 3 Check the hardware info at the control panel à Systems à Hardware à Device Manager and locate prolific **USB-to-Serial Com Port**.

(Must remember the port number because you will use it in later steps, if you didn't see any USB-to-serial port, please reinsert the USB connector.)




Upgrade ManGo

- 4 Install “**Flash Loader Demonstrator_V2.1.0_Setup.exe**” from the provided CD on your computer.




- 5 Run the upgrade software

and an interface will appears as below




- 6 Choose the corresponding “Port Name”, ”Baud Rate”, “Data Bits”, “Parity”, “Echo”, “Timeout” as below. (*Note: “Port Name” is the **USB-to-Serial Com Port***)




- 7 Take the battery out of ManGo

8 Press the “Confirm” button when you insert USB cable to ManGo.


9 Click “Next” button.




10 Click “Next” button.



11 Choose the download file from computer.



12 Click "Next" button.



13 Finish upgrade.

